Weibull Regression<sup>1</sup> STA312 Spring 2019

<sup>&</sup>lt;sup>1</sup>See last slide for copyright information.

Section 10.6 in the text, but it refers to a lot of things we have not covered yet.









## A multiplicative regression model Exponential model, just one explanatory variable

Independently for  $i = 1, \ldots n$ ,

$$t_i = e^{\beta_0 + \beta_1 x_i} \times \epsilon_i$$

where

 $\beta_0$  and  $\beta_1$  are unknown constants (parameters).

 $x_1, \ldots, x_n$  are known, observed constants.

 $\epsilon_1, \ldots, \epsilon_n$  are independent exponential(1) random variables.

 $t_1, \ldots, t_n$  are observed failure times.

 $\delta_1, \ldots, \delta_n$  are indicators for uncensored.

- These are sometimes called *accelerated failure time* models.
- Because the effect of  $x \neq 0$  is to *multiply* the failure time by a constant.

## Distribution of $t_i = e^{\beta_0 + \beta_1 x_i} \times \epsilon_i$ , with $\epsilon_i$ exponential(1)

- If  $\epsilon \sim \exp(1)$  and a > 0,  $x = a\epsilon$  is also exponential.
- Expected value a (or  $\lambda = 1/a$ ).
- Thus,  $E(t_i) = e^{\beta_0 + \beta_1 x_i} \Leftrightarrow \log E(t_i) = \beta_0 + \beta_1 x_i.$
- We are adopting a linear model for the log of the expected value.
- Or, we can transform the failure times by taking logs.

$$\log t_i = \beta_0 + \beta_1 x_i + \log \epsilon_i$$
$$= \beta_0 + \beta_1 x_i + \epsilon_i^*$$

where  $\epsilon_i^* = \log \epsilon_i \sim G(0, 1)$ .

Meaning of  $\beta_1$ With  $E(t_i) = e^{\beta_0 + \beta_1 x_i}$ 

- Increase  $x_i$  by one unit.
- The effect is to multiply  $E(t_i)$  by a constant.

$$e^{\beta_0 + \beta_1(x_i+1)} = c e^{\beta_0 + \beta_1 x_i}$$
  

$$\Leftrightarrow c = \frac{e^{\beta_0 + \beta_1(x_i+1)}}{e^{\beta_0 + \beta_1 x_i}}$$
  

$$= \frac{e^{\beta_0 + \beta_1 x_i + \beta_1}}{e^{\beta_0 + \beta_1 x_i}}$$
  

$$= e^{\beta_1}$$

- So when  $x_i$  is increased by one unit,  $E(t_i)$  is multiplied by  $e^{\beta_1}$ .
- If  $\beta_1 > 0$ ,  $E(t_i)$  goes up.
- If  $\beta_1 < 0$ ,  $E(t_i)$  goes down.

## Natural extensions

- More than one explanatory variable.
- Centering the quantitative explanatory variables.

$$t_i = \exp\{\beta_0 + \beta_1(x_{i,1} - \bar{x}_1) + \ldots + \beta_{p-1}(x_{i,p-1} - \bar{x}_{p-1})\} \cdot \epsilon_i$$

- In this case,  $e^{\beta_0}$  is the expected failure time for average values of all the explanatory variables.
- If there are dummy variables, center only the quantitative variables (covariates).

### Exponential

## Equivalent model on the log scale

Starting with  $t_i = \exp\{\beta_0 + \beta_1(x_{i,1} - \bar{x}_1) + \ldots + \beta_{p-1}(x_{i,p-1} - \bar{x}_{p-1})\} \cdot \epsilon_i$ 

$$\log t_i = \beta_0 + \beta_1 x_{i,1} + \ldots + \beta_{p-1} x_{i,p-1} + \log \epsilon_i$$
  
=  $\beta_0 + \beta_1 x_{i,1} + \ldots + \beta_{p-1} x_{i,p-1} + \epsilon_i^*$   
=  $\mathbf{x}_i^\top \boldsymbol{\beta} + \epsilon_i^*,$ 

where  $\epsilon_i^* \sim G(0, 1)$ .

- Recall, if  $Z \sim G(0, 1)$ , then  $\sigma Z + \mu \sim G(\mu, \sigma)$ .
- So the model says  $\log t_i \sim G(\mathbf{x}_i^\top \boldsymbol{\beta}, 1)$
- Why should the variance of log survival time be  $\frac{\pi^2}{6}$ ?
- Much more reasonable is  $\log t_i = \beta_0 + \beta_1 x_{i,1} + \ldots + \beta_{p-1} x_{i,p-1} + \sigma \epsilon_i^*$
- In this case,  $\log t_i \sim G(\mathbf{x}_i^\top \boldsymbol{\beta}, \sigma)$ .

Weibul

## Switching back to the time scale From the log time scale

$$\log t_{i} = \beta_{0} + \beta_{1} x_{i,1} + \ldots + \beta_{p-1} x_{i,p-1} + \sigma \epsilon_{i}^{*}$$
  
$$\Leftrightarrow \quad t_{i} = e^{\mathbf{x}_{i}^{\top} \boldsymbol{\beta}} e^{\sigma \epsilon_{i}^{*}} = e^{\mathbf{x}_{i}^{\top} \boldsymbol{\beta}} e^{\sigma \log \epsilon_{i}} = e^{\mathbf{x}_{i}^{\top} \boldsymbol{\beta}} e^{\log(\epsilon_{i}^{\sigma})}$$
  
$$\Leftrightarrow \quad t_{i} = e^{\mathbf{x}_{i}^{\top} \boldsymbol{\beta}} \epsilon_{i}^{\sigma}$$

We have arrived at the multiplicative regression model:

$$t_i = \exp\{\beta_0 + \beta_1 x_{i,1} + \ldots + \beta_{p-1} x_{i,p-1}\} \cdot \epsilon_i^{\sigma}$$

## $t_i = \exp\{\beta_0 + \beta_1 x_{i,1} + \ldots + \beta_{p-1} x_{i,p-1}\} \cdot \epsilon_i^{\sigma}$

- It's an accelerated failure time model. Changing one of the x values multiplies  $t_i$  by something.
- In particular, increase  $x_{i,k}$  by one unit while holding all other  $x_{i,j}$  values constant.
- Then  $t_i$  is multiplied by  $e^{\beta_k}$ .
- Holding  $x_{i,j}$  values constant is the meaning of "controlling" for explanatory variables in Weibull regression.
- Note that if  $\beta_k$  is negative,  $e^{\beta_k} < 1$  and  $t_i$  goes down.
- Call it a "negative relationship" (controlling for the other variables).
- If  $\beta_k$  is positive,  $e^{\beta_k} > 1$  and  $t_i$  goes up.
- Call this a "positive relationship" (controlling for the other variables).

### Weibull

## Distribution of $t_i$

Recall

- We have established that  $\log t_i \sim G(\mathbf{x}_i^\top \boldsymbol{\beta}, \sigma)$ .
- Exponential function of  $\text{Gumbel}(\mu, \sigma)$  is  $\text{Weibull}(\alpha, \lambda)$  with  $\lambda = e^{-\mu}$  and  $\alpha = 1/\sigma$ .
- Note that here,  $\mu_i = \mathbf{x}_i^\top \boldsymbol{\beta}$ .
- So,  $t_i$  is Weibull, with  $\lambda_i = e^{-\mathbf{x}_i^\top \boldsymbol{\beta}}$  and  $\alpha = 1/\sigma$ .

• This means

$$E(T_i) = \frac{\Gamma(1+\frac{1}{\alpha})}{\lambda} = e^{\mathbf{x}_i^\top \boldsymbol{\beta}} \Gamma(1+\sigma)$$
  
Median $(T_i) = \frac{[\log(2)]^{1/\alpha}}{\lambda} = e^{\mathbf{x}_i^\top \boldsymbol{\beta}} \log(2)^{\sigma}$   
 $h(t) = \alpha \lambda^{\alpha} t^{\alpha-1} = \frac{1}{\sigma} \exp\{-\frac{1}{\sigma} \mathbf{x}^\top \boldsymbol{\beta}\} t^{\frac{1}{\sigma}-1}$ 

### Weibull

### Conclusions Following from $\log t_i \sim G(\mathbf{x}_i^\top \boldsymbol{\beta}, \sigma)$

$$E(T_i) = e^{\mathbf{x}_i^\top \boldsymbol{\beta}} \Gamma(1+\sigma)$$
  
Median $(T_i) = e^{\mathbf{x}_i^\top \boldsymbol{\beta}} \log(2)^{\sigma}$   
$$h(t) = \frac{1}{\sigma} \exp\{-\frac{1}{\sigma} \mathbf{x}^\top \boldsymbol{\beta}\} t^{\frac{1}{\sigma}-1}$$

- Increasing value of  $x_j$  by c units multiplies the mean and median by  $e^{c\beta_j}$ .
- Same effect on the hazard function.
- Remarkable because the hazard function is a function of time t.
- And the effect is the same for every value of t.

## Proportional Hazards $h(t) = \frac{1}{\sigma} \exp\{-\frac{1}{\sigma} \mathbf{x}^{\top} \boldsymbol{\beta}\} t^{\frac{1}{\sigma} - 1}$

- Suppose two individuals have different  $\mathbf{x}$  vectors of explanatory variable values.
- They have different hazard functions because their  $\lambda$  values are different.
- Look at the *ratio*:

$$\frac{h_1(t)}{h_2(t)} = \frac{\frac{1}{\sigma} \exp\{-\frac{1}{\sigma} \mathbf{x}_1^\top \boldsymbol{\beta}\} t^{\frac{1}{\sigma}-1}}{\frac{1}{\sigma} \exp\{-\frac{1}{\sigma} \mathbf{x}_2^\top \boldsymbol{\beta}\} t^{\frac{1}{\sigma}-1}} \\ = \frac{\exp\{-\frac{1}{\sigma} \mathbf{x}_1^\top \boldsymbol{\beta}\}}{\exp\{-\frac{1}{\sigma} \mathbf{x}_2^\top \boldsymbol{\beta}\}} \\ = \exp\{\frac{1}{\sigma} (\mathbf{x}_2 - \mathbf{x}_1)^\top \boldsymbol{\beta}\}$$

The point is that  $h_1(t)$  and  $h_2(t)$  are always in the same proportion for every value of t.

#### Weibul

# Proportional Hazards $h_1(t) = 2 h_2(t)$ with $\sigma = 2$



#### Weibu

# Proportional Hazards $h_1(t) = 2 h_2(t)$ with $\sigma = 1/3$



## Copyright Information

This slide show was prepared by Jerry Brunner, Department of Statistics, University of Toronto. It is licensed under a Creative Commons Attribution - ShareAlike 3.0 Unported License. Use any part of it as you like and share the result freely. The LATEX source code is available from the course website:

http://www.utstat.toronto.edu/~brunner/oldclass/312s19